

Joystick

Hardware Overview

What is it?

The **Joystick** (Model KY-023) is your main input device for movement. On the K-Comp, you can use it to control a character in a game, steer a robot, or navigate menus.

Electrical Explanation

Inside the joystick, there are **two potentiometers** (variable resistors) at a 90° angle to each other.

- One measures the **Left/Right** movement.
- One measures the **Up/Down** movement.

As you move the stick, it turns the internal wipers, changing the resistance. This changes the output voltage between 0V and 5V. The Processor reads this voltage and converts it into a number.

- **Connection (Y-Axis):** Connected to **Analog Pin A1**.
- **Connection (X-Axis):** Connected to **Analog Pin A2**.
- **Signal Flow:** Movement → Resistance Change → Voltage Change (0–5V) → ADC (Analog to Digital Converter) → Digital Number.

How Coordinates Work: The "Centered" System

Standard analog inputs read a value from 0 to 1023. However, the **K-Comp library** automatically does the math to make the **center position 0**.

- **Negative Numbers:** left or down.
- **Positive Numbers:** right or up.
- **Zero:** center (resting position).

Stick Position	Raw Value	K-Comp Library Value
Left	0	-512
Center	~512	0
Right	1023	+511

Software & Programming

`kcomp_joystick.h`

This library processes the raw data for you. It can calculate the **Direction** (e.g., "UP_LEFT") and the **Intensity** (0–100%) automatically. **Usage:** `#include <kcomp_joystick.h>`.

Function Reference

Function Name	Description & Parameters
<code>void initJoystick()</code>	Description: Initializes the joystick. Sets pins A1 and A2 as inputs. Usage: Must be called once inside <code>setup()</code> .
<code>int getJoystickXValue()</code>	Description: Gets the position of the X-axis (horizontal). Returns: A value from -512 (left) and +511 (right).
<code>int getJoystickYValue()</code>	Description: Gets the position of the Y-axis (vertical). Returns: A value from -512 (Down) and +511 (Up).
<code>joystickState getJoystickState()</code>	Read Everything: The "All-in-One" function. Returns: A <code>joystickState</code> structure containing both <code>.direction</code> and <code>.intensity</code> calculated for you.

Joystick Directions (States)

When you access `state.direction`, it will be exactly **one** of the values:

JOYSTICK_CENTER, JOYSTICK_UP,	How to use it?
JOYSTICK_DOWN, JOYSTICK_LEFT,	
JOYSTICK_RIGHT, JOYSTICK_UP_LEFT,	<code>if (state.direction == JOYSTICK_UP_RIGHT)</code>
JOYSTICK_UP_RIGHT, JOYSTICK_DOWN_LEFT,	<code>{</code>
JOYSTICK_DOWN_RIGHT, JOYSTICK_UNDEFINED	<code> // Move character diagonally</code>
	<code>}</code>

Pitfall: The "Deadzone" (Gap)

Mechanical joysticks are never perfect; when you let go, they might not settle at exactly 0 (it might be 2 or -5). Hence, the library ignores any movement smaller than 50.

Sample Program

This program prints the direction and intensity to the Serial Monitor.

```
#include <kcomp_joystick.h>

void setup() {
    Serial.begin(115200);
    initJoystick();           // Initialize the hardware
    Serial.println("Joystick Ready!");
}

void loop() {
    // Get the calculated state (Direction + Intensity)
    joystickState state = getJoystickState(); //

    // Print Intensity (0% to 100%)
    Serial.print("Speed: ");
    Serial.print(state.intensity);
    Serial.print("%");

    // Check specific directions
    if (state.direction == JOYSTICK_UP) {
        Serial.println(" -> Moving UP");
    }
    else if (state.direction == JOYSTICK_CENTER) {
        Serial.println(" -> Stopped");
    }

    delay(200);
}
```

 **Try it out:** You can find the full sample program **SimpleJoystick** in the K-Comp examples folder!